



# QuarkXPress Server 8.12 ReadMe

# Contents

<b>QuarkXPress Server 8.12 ReadMe.....</b>	<b>3</b>
<b>System requirements.....</b>	<b>4</b>
<b>Mac OS.....</b>	<b>4</b>
Software.....	4
Hardware.....	4
<b>Windows.....</b>	<b>4</b>
Software.....	4
Hardware.....	5
<b>Installing QuarkXPress Server on Mac OS.....</b>	<b>6</b>
<b>Installing QuarkXPress Server on Windows.....</b>	<b>8</b>
Existing QuarkXPress Server instance on Windows.....	9
<b>Introduction to QLA Server.....</b>	<b>11</b>
<b>Uninstalling.....</b>	<b>12</b>
<b>Mac OS.....</b>	<b>12</b>
<b>Windows.....</b>	<b>12</b>
<b>What's new in QuarkXPress Server 8.1.....</b>	<b>13</b>
<b>Contacting Quark.....</b>	<b>15</b>
In the Americas.....	15
Outside the Americas .....	15
In Australia.....	15
<b>Legal notices.....</b>	<b>16</b>

# QuarkXPress Server 8.12 ReadMe

QuarkXPress® Server is a high-fidelity content-composition and rendering server application. It is built on multiple technologies derived from QuarkXPress. Through a network connection and a browser, QuarkXPress Server can return rendered versions of QuarkXPress pages in a variety of formats. This document provides information about QuarkXPress Server software.

- ➔ Installation instructions for QuarkXPress Server Manager are included in the *QuarkXPress Server Manager ReadMe* file.

# System requirements

## Mac OS

### Software

- Mac OS® X Server 10.4.11, 10.5.8, 10.6 or later (Mac OS X 10.4.11 Client minimum)
- Java™ J2SE™ Runtime Environment (JRE™) 1.5 or 1.6

➔ Mac OS X 10.4.11 or later Client OS is supported for development, but is not recommended for production server deployments.

### Hardware

- Quad-core Mac Pro® or Xserve® system minimum
- 8GB RAM minimum
- 150 GB available hard disk space minimum
- TCP/IP network

➔ PowerPC® systems are not recommended.

## Windows

### Software

- Windows® 2003 Server or Windows 2008 Server (Windows XP minimum)

➔ Windows XP, Windows Vista®, and Windows 7 are supported for development, but are not recommended for production server deployments.

➔ The size of the QuarkXPress Server document pool used with a file server subsystem determines the required hard disk space.

➔ A RAID 0 setup of two or more hard disks increases system throughput. RAID 0 is not fault-tolerant, so you must perform frequent backups.

### Hardware

- Intel® or AMD dual-core processor for three or fewer subrenderers; Intel or AMD quad-core processor for heavy loads with four or more subrenderers
- 4GB RAM minimum
- 150MB hard disk space minimum
- TCP/IP network

# Installing QuarkXPress Server on Mac OS

To install QuarkXPress Server:

- 1 Disable any virus protection software. If you are concerned about a virus infecting your computer, run a virus check on the installer file and then disable your virus detection software.
- 2 Double-click the Installer icon and follow the instructions on the screen.
- 3 When prompted, enter the validation code.
- ➔ Do not discard the validation code. You will need it if you have to reinstall.
- 4 In the **User Information** screen, enter your name and company name, and click **Continue**.
- ➔ The **User Information** screen also displays your QuarkXPress Server software serial number.
- 5 In the **QLA License Server Details** screen, enter the IP address and port number of the main Quark® License Administrator (QLA) server in the **License Server IP Address** and **License Server Port Number** fields. Optionally, enter the IP address and port number of a backup QLA server in the **Backup Server IP Address** and **Backup Server Port Number** fields.
- 6 In the **Port and Folder Settings** screen:
  - Check **Enable HTTP Interface** to enable the built-in HTTP 1.0 server of QuarkXPress Server, and enter a value in the **Port** field. The default value is 8080.
  - Check **Enable the File System Document Pool** to designate the document pool for QuarkXPress Server. If **Enable the File System Document Pool** is checked, you can click **Browse** to navigate to a folder. Selecting that folder designates it as the document pool folder.
  - Check **Enable Logging** to enable error and transaction logging. If **Enable Logging** is checked, you can click **Browse** to navigate to a folder. Selecting that folder designates it as the log folder.

- Check **Create Preferences in Application Folder** to have QuarkXPress Server create its preferences files in the QuarkXPress Server application folder. Otherwise, preferences are created at the following location:  
`[drive]:Users:[username]:Library:Preferences:Quark.`
- ➔ QuarkXPress Server creates a "Preferences" folder for each subrenderer. For example, if you have four subrenderers, QuarkXPress Server creates a master "Preferences" folder and four "Preferences" folders for the subrenderers (that is, "Preferences," "Preferences sub1," "Preferences sub2," "Preferences sub3," and "Preferences sub4").
- 7** In the **Install As Service** screen, enter the number of subrenderers you want to run. The number of available subrenderers is determined by the QLA license file. If you leave this field blank, one subrenderer is assumed.
- ➔ The installer creates a file named "QuarkXPressServer.config" at the root level of the QuarkXPress Server application folder. This file contains the startup parameters for QuarkXPress Server, including the number of subrenderers you want to launch.
- 8** Also in the **Install As Service** screen, you can check **Install QuarkXPress Server as a Service**. If you check this box, you will not have a user interface for modifying QuarkXPress Server.
- 9** Click **Continue**. The **Select a Destination** screen displays the drive where QuarkXPress Server will be installed.
- ➔ By default, the installer installs QuarkXPress Server in the "Applications" folder.
- 10** The **Installation Type** screen provides two options from the same button: **Customize** and **Easy Install**. If you click **Customize**, you can selectively install the application, XTensions software files, and color files, and you can select a different installation location. The **Customize** button changes to **Easy Install**. If you click **Easy Install**, the installer installs all QuarkXPress Server files.

# Installing QuarkXPress Server on Windows

To install QuarkXPress Server:

- 1 Disable any virus protection software. If you are concerned about a virus infecting your computer, run a virus check on the installer file and then disable your virus detection software.
- 2 Double-click the Installer icon and follow the instructions on the screen.  
If you already have an installation of QuarkXPress Server on Windows, you can replace, repair, or modify the software, or you can install a new instance. For more information, see [Existing QuarkXPress Server instance on Windows](#).
- 3 When prompted, enter your name and company name.
- 4 Enter the validation code.

➔ Do not discard the validation code. You will need it if you have to reinstall.

- 5 When the **License Administrator Service** screen displays, enter the IP address and port number of the main Quark License Administrator (QLA) server in the **License Server IP Address** and **License Server Port Number** fields. Optionally, enter the IP address and port number of a backup QLA server in the **Backup Server IP Address** and **Backup Server Port Number** fields.
- 6 When the **Port and Folder Settings** dialog box displays:
  - Check **Enable HTTP Interface** to enable the built-in HTTP 1.0 server of QuarkXPress Server. Enter a value in the **Port** field. The default value is 8080.
  - Check **Enable File System Document Pool** to designate the document pool for QuarkXPress Server. If **Enable File System Document Pool** is checked, you can click **Browse** to navigate to a folder. Selecting that folder designates it as the document pool folder.
  - Check **Enable Logging** to enable error and transaction logging. If **Enable Logging** is checked, you can click **Browse** to navigate to a folder. Selecting that folder designates it as the log folder.



- Check **Create Preferences in Application Folder** to have QuarkXPress Server create its preferences files in the QuarkXPress Server application folder. Otherwise, QuarkXPress Server creates preferences files at the following location:

*Windows 2003 and Windows XP:* [boot drive]:\Documents and Settings\[User Name]\Application Data\Quark

*Windows 2008 and Windows Vista when QuarkXPress Server is running as a service under a local system user account:* C:\ProgramData\Quark\QuarkXPress Server 8\Preferences

*Windows 2008 and Windows Vista when QuarkXPress Server is running normally or as a service under a domain user account:*

C:\Users\Administrator\AppData\Local\Quark\QuarkXPress Server 8

### 7 Click Next.

The next screen displays the drive and folder where QuarkXPress Server will be installed. To install QuarkXPress Server elsewhere, click **Browse** and navigate to the desired folder.

- 8 Insert the number of available subrenderers that you require QuarkXPress Server to run by default.
- 9 If you check **Install QuarkXPress Server as a Service**, you can choose **Local** or **Domain** from the **Choose System** drop-down menu. If you choose **Domain**, enter values in the **Domain**, **User**, and **Password** fields.
- 10 When the **Select Setup Type** screen displays, you can click **Complete** to install all QuarkXPress Server files. Alternatively, you can click **Custom** to selectively install the XTensions software files, color files, and language dictionary files.
- 11 When the installation completes, click **Finish**. An alert indicates that default security settings will prohibit applications from uploading new templates/images to the QuarkXPress Server document pool.
- 12 To enable file uploading, click **Yes**. The installer adds QuarkXPress Server to the exceptions list in the **Exceptions** tab of the **Windows Firewall** dialog box.

### Existing QuarkXPress Server instance on Windows

If you already have QuarkXPress Server installed, you can install a new instance of the software, or you can replace or modify your QuarkXPress Server installation.

- 1 Disable any virus protection software. If you are concerned about a virus infecting your computer, run a virus check on the installer file and then disable your virus detection software.
- 2 Double-click the Installer icon and follow the instructions on the screen.

If you already have an installation of QuarkXPress Server on Windows, the **Existing Installed Instances Detected** screen displays with three options:

## INSTALLING QUARKXPRESS SERVER ON WINDOWS

- **Install a new instance of this application**
  - **Maintain the instance of application selected below**
  - **Uninstall the instance of application selected below and install a new instance of version 8.1**
- 3** If you click **Install a new instance of this application**, you can retain your existing QuarkXPress Server installation and create a new instance. Follow the installation procedures described above until you successfully install QuarkXPress Server.
  - 4** If you click **Maintain the instance of application selected below** in the **Existing Installed Instances Detected** screen, click **Next**.  
The **Preparing Setup** screen displays, followed by the **QuarkXPress Server Setup Maintenance program Welcome** screen.
    - Click **Modify** to choose new program features to add or to choose currently installed features to remove.
    - Click **Repair** to reinstall all program features installed by the previous setup.
    - Click **Remove** to remove all installed features.
  - 5** When the **Maintenance Complete** screen displays, click **Finish**.
  - 6** If you click **Uninstall the instance of application selected below and install a new instance of version 8.1** in the **Existing Installed Instances Detected** screen, the installer removes the selected instance of QuarkXPress Server and install a new instance.
  - 7** Click **Finish** when the process completes.

# Introduction to QLA Server

QLA Server is the software component that issues licenses to the Quark application clients. After you install Quark License Administrator Server, download your license file from the Quark Web site. The server can be any computer on the network that meets the minimum system requirements. The server monitors license usage over the network and grants licenses to the client computers.

QLA clients are the computers on which Quark applications are installed — for example, QuarkXPress, Quark Publishing System® (QPS®), or QuarkXPress Server software. When a user attempts to launch a Quark application on a client computer, the client sends a request to the QLA Server. The server, which is always listening for requests, determines whether there is an available license. If there is, then the server grants a license and the client computer can launch the Quark application. If no licenses are available, the server does not grant a license. When this occurs, the Quark application does not launch.

In the QLA Control Panel application, the **Configuration Options** tab lets you specify how QLA monitors licenses. This tab includes the **Server Configuration** area and the **Extended Check-out Configuration** area. In the **Server Configuration** area:

- The **Heartbeat Interval (Seconds)** value lets you specify the number of seconds between attempts by the client to reach the server. If a Quark application fails to successfully connect to the server within this time, then that application automatically attempts to reconnect.
- The **Heartbeat Retries** field lets you specify the number of times a client can attempt to make a connection before reporting a connection failure.

For example: If the **Heartbeat Interval (Seconds)** value is 3600 (one hour) and the **Heartbeat Retries** value is 10, the system waits 10 hours before failing. If the client is able to successfully connect with the server on or before the tenth attempt, outstanding licenses are restored. If not, the application checks in all allocated licenses.

# Uninstalling

- ➔ If the uninstaller detects a running instance of the application, an alert displays. Close the application before you begin to uninstall.

## Mac OS

To uninstall QuarkXPress Server, open the "Applications" folder on your hard drive (or the folder in which QuarkXPress Server was installed) and drag the QuarkXPress Server 8 folder to the trash.

## Windows

To uninstall QuarkXPress Server:

- 1 Choose **Start > All Programs > QuarkXPress Server 8 > Uninstall QuarkXPress Server 8**.
- 2 Click **Yes**. The uninstaller gathers the information necessary for uninstalling and then uninstalls the software.

Alternatively, you can run the installer again, click **Maintain or update the instance of this application selected below**, click **Remove**, and click **Finish** when the removal process completes.

# What's new in QuarkXPress Server 8.1

The new features in QuarkXPress Server 8.1 include the following. For more information, see *A Guide to QuarkXPress Server 8.1* and the *QuarkXPress Server 8.1 Web Integration Guide*.

- The ability to construct, deconstruct, modify, and apply drop shadows to groups and anchored groups
- Support for exporting Print layouts and Interactive layouts as SWF (Flash) files
- The ability to check a project for missing fonts, for missing pictures, and for a platform designation that is different from the platform on which QuarkXPress Server is running
- The ability to save a QuarkXPress project file as a template or save a QuarkXPress template as a project
- The ability to save a QuarkCopyDesk article file as a template or save a QuarkCopyDesk template as an article
- The ability to include a page picture when exporting an article from a QuarkXPress layout
- The ability to move pages prior to rendering
- The ability to control the inclusion of fonts in exported EPS files
- The ability to render blank pages when creating EPS files
- The ability to describe item positions in spread-based coordinates when constructing, deconstructing, and modifying projects in XML
- The ability to resize a box to fit its content
- The ability to apply section-specific numbering and formatting to automatic page numbers
- The ability to differentiate between intrinsic fonts and software-generated "faux" bold/italic fonts
- Support for picture background colors
- The ability to clear a picture from a picture box
- The ability to specify which page of an imported PDF should be displayed in a box
- The ability to control corner style for boxes
- The ability to apply a skew value to boxes
- Support for Mojigumi sets

## WHAT'S NEW IN QUARKXPRESS SERVER 8.1

- The ability to link text boxes to table cells
- The ability to export PDF files with native transparency (**Server/QuarkXPress Server > Document Controls > Output Styles > PDF style > Edit PDF Style dialog box > Transparency pane > Export Transparency Natively**)

# Contacting Quark

If you have questions about installing, configuring, or using this software, please contact Quark Inc.

## In the Americas

For enterprise product technical support (QPS and QuarkXPress Server), please call 800.788.0045 between 7:00 a.m. and 6:00 p.m. Mountain Time, Monday through Friday, or send an e-mail message to [enterprisesupport@quark.com](mailto:enterprisesupport@quark.com).

For desktop product technical support (QuarkXPress and QuarkCopyDesk®), please visit the Quark Web site at [www.quark.com](http://www.quark.com). Live online chat is available between 12:00 a.m. Monday and 11:59 p.m. Friday (Mountain Time), or send an e-mail message to [techsupp@quark.com](mailto:techsupp@quark.com).

For product information, please visit the Quark Web site at [www.quark.com](http://www.quark.com), or send an e-mail message to [cservice@quark.com](mailto:cservice@quark.com).

## Outside the Americas

Technical support is available by phone between 8.30 and 17.30 Central European Time, Monday through Friday, or by sending an e-mail message to [enterprisesupport@quark.com](mailto:enterprisesupport@quark.com).

From Austria, Belgium, Denmark, France, Germany, Ireland, Luxembourg, The Netherlands, and the United Kingdom, please call 00800 2505 2606.

From all other countries outside the Americas, please call +41 32 720 14 14.

For product information, please visit the Quark Web site at [euro.quark.com](http://euro.quark.com), or send an e-mail message to [eurocservice@quark.com](mailto:eurocservice@quark.com).

## In Australia

For technical support, please call 1800.670.973 between 10:00 a.m. and 7:00 p.m. Sydney Time (AEST), Monday through Friday, or send an e-mail message to [austechsupp@quark.com](mailto:austechsupp@quark.com).

# Legal notices

©2009 Quark Inc. as to the content and arrangement of this material. All rights reserved.

Protected by one or more of U.S. Patent Nos. 5,541,991, 5,907,704, 6,005,560, 6,052,514, 6,081,262, 6,947,959 B1, 6,940,518 B2, 7,116,843 and other patents pending.

©1986-2009 Quark Inc. and its licensors as to the technology. All rights reserved. Quark Products and materials are subject to the copyright and other intellectual property protection of the United States and foreign countries. Unauthorized use or reproduction without Quark's written consent is prohibited. QUARK IS NOT THE MANUFACTURER OF THIRD PARTY SOFTWARE OR OTHER THIRD PARTY HARDWARE (HEREINAFTER "THIRD PARTY PRODUCTS") AND SUCH THIRD PARTY PRODUCTS HAVE NOT BEEN CREATED, REVIEWED, OR TESTED BY QUARK, THE QUARK AFFILIATED COMPANIES OR THEIR LICENSORS. (QUARK AFFILIATED COMPANIES SHALL MEAN ANY PERSON, BRANCH, OR ENTITY CONTROLLING, CONTROLLED BY OR UNDER COMMON CONTROL WITH QUARK OR ITS PARENT OR A MAJORITY OF THE QUARK SHAREHOLDERS, WHETHER NOW EXISTING OR FORMED IN THE FUTURE, TOGETHER WITH ANY PERSON, BRANCH, OR ENTITY WHICH MAY ACQUIRE SUCH STATUS IN THE FUTURE.)

QUARK, THE QUARK AFFILIATED COMPANIES AND/OR THEIR LICENSORS MAKE NO WARRANTIES, EITHER EXPRESS OR IMPLIED, REGARDING THE QUARK PRODUCTS/SERVICES AND/OR THIRD PARTY PRODUCTS/SERVICES, THEIR MERCHANTABILITY, OR THEIR FITNESS FOR A PARTICULAR PURPOSE. QUARK, THE QUARK AFFILIATED COMPANIES AND THEIR LICENSORS DISCLAIM ALL WARRANTIES RELATING TO THE QUARK PRODUCTS/SERVICES AND ANY THIRD PARTY PRODUCTS/SERVICES. ALL OTHER WARRANTIES AND CONDITIONS, WHETHER EXPRESS, IMPLIED OR COLLATERAL, AND WHETHER OR NOT, MADE BY DISTRIBUTORS, RETAILERS, XTENSIONS DEVELOPERS OR OTHER THIRD PARTIES ARE DISCLAIMED BY QUARK, THE QUARK AFFILIATED COMPANIES AND THEIR LICENSORS, INCLUDING WITHOUT LIMITATION, ANY WARRANTY OF NON-INFRINGEMENT, COMPATIBILITY, OR THAT THE SOFTWARE IS ERROR-FREE OR THAT ERRORS CAN OR WILL BE CORRECTED. THIRD PARTIES MAY PROVIDE LIMITED WARRANTIES AS TO THEIR OWN PRODUCTS AND/OR SERVICES, AND USERS MUST LOOK TO SAID THIRD PARTIES FOR SUCH WARRANTIES, IF ANY. SOME JURISDICTIONS, STATES OR PROVINCES DO NOT ALLOW LIMITATIONS ON IMPLIED WARRANTIES, SO THE ABOVE LIMITATION MAY NOT APPLY TO PARTICULAR USERS.



IN NO EVENT SHALL QUARK, THE QUARK AFFILIATED COMPANIES, AND/OR THEIR LICENSORS BE LIABLE FOR ANY SPECIAL, INDIRECT, INCIDENTAL, CONSEQUENTIAL OR PUNITIVE DAMAGES, INCLUDING, BUT NOT LIMITED TO, ANY LOST PROFITS, LOST TIME, LOST SAVINGS, LOST DATA, LOST FEES, OR EXPENSES OF ANY KIND ARISING FROM INSTALLATION OR USE OF THE QUARK PRODUCTS/SERVICES, IN ANY MANNER, HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY. IF, NOTWITHSTANDING THE FOREGOING, QUARK, THE QUARK AFFILIATED COMPANIES AND/OR THEIR LICENSORS ARE FOUND TO HAVE LIABILITY RELATING TO THE QUARK PRODUCTS/SERVICES OR THIRD PARTY PRODUCTS/SERVICES, SUCH LIABILITY SHALL BE LIMITED TO THE AMOUNT PAID BY THE USER TO QUARK FOR THE SOFTWARE/SERVICES AT ISSUE (EXCLUDING THIRD PARTY PRODUCTS/SERVICES), IF ANY, OR THE LOWEST AMOUNT UNDER APPLICABLE LAW, WHICHEVER IS LESS. THESE LIMITATIONS WILL APPLY EVEN IF QUARK, THE QUARK AFFILIATED COMPANIES, THEIR LICENSORS AND/OR THEIR AGENTS HAVE BEEN ADVISED OF SUCH POSSIBLE DAMAGES. SOME JURISDICTIONS, STATES OR PROVINCES DO NOT ALLOW THE EXCLUSION OR LIMITATION OF INCIDENTAL OR CONSEQUENTIAL DAMAGES, SO THIS LIMITATION OR EXCLUSION MAY NOT APPLY. ALL OTHER LIMITATIONS PROVIDED UNDER APPLICABLE LAW, INCLUDING STATUTES OF LIMITATION, SHALL CONTINUE TO APPLY.

IN THE EVENT ANY OF THESE PROVISIONS ARE OR BECOME UNENFORCEABLE UNDER APPLICABLE LAW, SUCH PROVISION SHALL BE MODIFIED OR LIMITED IN ITS EFFECT TO THE EXTENT NECESSARY TO CAUSE IT TO BE ENFORCEABLE.

USE OF THE QUARK PRODUCTS IS SUBJECT TO THE TERMS OF THE END USER LICENSE AGREEMENT OR OTHER APPLICABLE AGREEMENTS FOR SUCH PRODUCT/SERVICE. IN THE EVENT OF A CONFLICT BETWEEN SUCH AGREEMENTS AND THESE PROVISIONS THE RELEVANT AGREEMENTS SHALL CONTROL.

Quark, the Quark logo, QuarkXPress, XTensions, Quark Publishing System, and QPS are trademarks or registered trademarks of Quark Inc. and its affiliates in the U.S. and/or other countries.

Windows is a registered trademark of Microsoft Corporation in the United States and/or other countries. PowerPC is a registered trademark of International Business Machines Corporation. Intel is a registered trademark of Intel Corporation. Java and all Java based marks are trademarks or registered trademarks of Sun Microsystems, Inc. in the United States and other countries. Mac OS, Xserve and Mac Pro are trademarks of Apple Inc. registered in the U.S. and other countries. All other marks are the property of their respective owners.